

# Installing an apk file to Pico headsets

## Step 1 Enable developer mode for your headset

### Pico G2:

- From the **Main Menu** open **Settings**
- Make sure you are running the latest PUI version by clicking **Check PUI Update** on the right side of the settings panel
- From settings panel select **General**
- Click **Software version** 10 times
- A **Developer** button should appear below the **General** button. This means you are now in developer mode!

### Pico Neo 2:

- In the main menu of your headset, go to **Settings**
- Click **Advanced Settings**
- Scroll down and Click **System**
- Scroll down and click **About Device**
- Click **PUI Version 10 times** to enable Developer Mode
- Go back and click **Developer options**
- Scroll down and enable **USB debugging**

## Step 2 Connect headset to PC

Use a USB cable to connect your Pico headset to a PC

## Step 3 Move apk file to the headset

Navigate to **This PC** and double click your headset to show the files inside the headset. Drag the apk file you downloaded to headset files.

## Step 4 Install the apk

Turn on your headset. In the headset, navigate to the apk file you previously dragged to the headset. Click the apk file - your headset will now start installing 360Mediaplayer. 360Mediaplayer is now ready to be used. Navigate to it using your headsets file browser.

You can also use [SideQuest](#) to install apk's.